

Encompass EPC Admin Guide

Version 5

Last Update: 12-4-2025



Contents

Contents	2
Change History	2
Overview	3
2026 SDK to EPC Transition Requirements	3
Overview	3
Critical Dates	3
FAQs	3
Setting up the API connection – LoanBeam Administrators only	4
Copying existing Encompass Token from LoanBeam.....	4
Overview	4
Creating New API token in LoanBeam	4
Overview	4
Create LoanBeam EPC service and add LoanBeam credentials.....	9
Overview	9

Change History

Date	Change	Author
8/21/2025	Document creation	Shannon Redican
8/21/2025	Updating format and verbiage	Roby Robertson
8/22/2025	Updating EPC information	Shannon Redican
9/26/2025	Updated dates for EPC conversion	Shannon Redican
12/2/2025	Updated critical dates	Shannon Redican
12/4/2025	Add SDK Desktop instructions	Jean Ballard / Krishan Sammi/Shannon Redican

Overview

LoanBeam automates income calculation and file review, dramatically reducing the time and effort spent extracting, inputting, and validating data for borrowers. And with direct connections to Freddie Mac® and Fannie Mae®, it offers a direct path to income rep and warranty assessment.

This document is intended to explain the functionality of the LoanBeam/**Encompass EPC** integration.

2026 SDK to EPC Transition Requirements

Overview

LoanBeam clients using Encompass SDK (desktop) will need to migrate to Encompass EPC by **12/31/2026**.

To complete that migration, Administrators will need to:

- **Connect** LoanBeam to the EPC service using their existing LoanBeam credentials.
- **Activate** the “**LoanBeam EPC**” service inside Encompass EPC for users.

Critical Dates

- **12/31/2026** – SDK integration deprecated.

FAQs

Q: How long will I be able to use my existing SDK integration?

A: Until 12/31/2026

Q: Will I be able to test EPC before SDK is deprecated?

A: Yes. SDK and EPC can be used simultaneously until 12/31/2026.

Q: Will applications processed via the SDK integration be viewable in the EPC interface?

A: Yes. LoanBeam applications created for a loan using the SDK integration will be accessible via the new EPC interface.

Q: What if I am using IP Authentication on the LoanBeam website?

A: The LoanBeam integration with Encompass Partner Connect (EPC) utilizes the ICE Encompass security settings and does not reference LoanBeam IP Authentication settings.

Setting up the API connection – LoanBeam Administrators only

To establish the connection between LoanBeam and Encompass, you must first establish the API (Application programming interface) connection. (Note: This is a one-time event.)

Important Note!

Before you begin the steps outlined below, make sure you meet the following parameters:

- You are an Administrator User to Encompass and LoanBeam.
- You have successfully logged in to LoanBeam.
- You have used the SAME email address for Encompass and LoanBeam.

Examples:

LoanBeam	Encompass	Status
johnny.somebody@email.com	johnny.somebody@email.com	Acceptable
johnny.somebody@email.com	jsomebody@email.com	Not Acceptable
johnny.somebody@email.com	johnny.somebody@othermail.com	Not Acceptable

Copying existing Encompass Token from LoanBeam

Overview

For clients who have an existing API token connected to Encompass AND **would like to reuse** that for their EPC integration, **they may just copy the existing token.**


To copy the existing token, access the API token within your LoanBeam Admin portal by completing steps 1 through 3 in the below steps. Then, copy the API token as outlined in step 9.

Creating New API token in LoanBeam

Overview


For clients that would like to create a new API token for this new EPC integration, complete the following steps.

1. Log into your LoanBeam dashboard (secure.loanbeam.com)




The image shows the LoanBeam login page. At the top is the LoanBeam logo with the tagline "NOW PART OF LOANLOGICS". Below the logo are two input fields: "Email address" and "Password". To the left of the "Password" field is a link that says "Forgot Your password?". To the right of the "Password" field is a green "Login" button. At the bottom, there is a link "New to LoanBeam?" followed by a "Learn More" link.

2. Navigate to the dark-grey drop-down box at the top right of the screen containing your name at the top right of the LoanBeam dashboard, click "Admin."



The image shows the top navigation bar of the LoanBeam dashboard. On the left, it says "Units Remaining: 49". In the center, there is a "Help Center" button with a question mark icon and an "Applications" dropdown menu. On the right, there is a dark-grey drop-down box containing the user's name "Robby" and several options: "Admin", "Change Password", and "Logout". The "Admin" option is highlighted with a red box. Below the navigation bar, there are buttons for "Column Setup", "Clear Filter", "New", "Edit", and "Cancel". There is also a table with columns "First Name" and "Files Uploaded", and a row with the value "38".


3. Click "LoanBeam API" from the top menu.



The image shows the top menu of the LoanBeam dashboard. The menu items are "User Management", "Account Setup", "Billing & Reports", "LoanBeam API", and "API Authentication". The "LoanBeam API" item is highlighted with a red box. Below the menu, there are links for "Token Creation" and "Webhook Settings".

(Continued on next page.)


4. Enable token access by checking the “Enabled” box.



Token Access : ☒ Enabled Add Token

Edit	Delete	Token Key	Token Name	Created On
------	--------	-----------	------------	------------


5. Create a LoanBeam API token by clicking “Add Token.”



Token Access : ☒ Enabled Add Token

Edit	Delete	Token Key	Token Name	Created On
------	--------	-----------	------------	------------


6. Create a name for the token, for example, “Encompass EPC.” Then, click “Create.”



Encompass EPC

Create Cancel


7. Check the “Enabled” box on “Password Access” row.



Password Access : ☒ Enabled

Download File Token : FileDownload token expiry

8. Click “Save.”



Password Access : ☒ Enabled

Download File Token : FileDownload token expiry


☒ Never

☐ Single Use


☐ After Seconds

Save

Note! If you are unable to see the save button at the bottom of the screen, zoom out on your browser by holding CTRL and pushing the “-” button.




9. Copy the API key to your clipboard by clicking and dragging your mouse across the number and pressing "CTRL+C" on your keypad.



10. Continue onto Encompass EPC's Admin dashboard.

Note For Desktop Users Only

To use LoanBeam through Encompass Desktop, you must complete a one-time process to enable the web-version settings. Click **Encompass Settings** then **Web Version Settings** to proceed.




Create LoanBeam EPC service and add LoanBeam credentials

Overview


Clients who have completed the process to copy or create an API token in LoanBeam complete the following steps.

11. Log in to Encompass EPC <https://encompassloconnect.com>




(Continued on next page.)

12. Navigate to top right corner panel and click on “Admin” to launch Admin console.




(Continued on next page.)

13. Navigate to panel on left side of screen and click on “Services.”




14. Click on “Services Management” which is in the list under “Services”. This will launch the Services panel.




(Continued on next page.)


- Click on the three vertical dots next to "Service Setup", then click on "Service Setup" from the dropdown menu.



- Click on "Add" to add a new user to the related service.




17. If edits are required for an existing user, click on the Pencil icon.



(Continued on next page.)

18. To add a new service or edit an existing service, the following information is needed:

- a. Name of service
 - i. User discretion; Example: *LoanBeam EPC*
- b. Description of service
 - i. Optional, but recommended; Example: *This is LoanBeam Income Service. Contact your account administrator if changes are needed.*
- c. Select an individual or group that is authorized to use this service.
 - i. User discretion; Example: *LoanBeam User or LoanBeam Usergroup*



The screenshot shows the 'Encompass | ADMIN' interface. The left sidebar contains navigation options: COMPANY/USER SETUP, SERVICES (highlighted), Automated Ordering Templates, Vendor Allocation, Data Permissions, OPPORTUNITIES SETUP, WORKFLOW MANAGEMENT, ASSET MANAGEMENT, and CUSTOMIZATION. The main content area is titled 'Services Management / Service Setups / Edit Manual Setup'. It includes an 'Active' toggle switch set to 'ON'. The service details are as follows:

- Service Type:** Additional Services
- Evaluation Level:** Loan Level
- Provider:** LoanBeam (EPC) - Dev1
- Service Setup Name ***: Loanbeam (highlighted with a red box)
- Service Setup Description**: (empty field, highlighted with a red box)
- Readiness Conditions**: Includes a 'Condition Editor' (selected) and a 'Query Builder' option. There are 'Validate' and 'Evaluate' buttons.
- Authorized Users**: (highlighted with a red box)
- Category Selection**: A table with columns 'Category' and 'Selected Entities'. The 'Category' column lists 'Organizations', 'Users', and 'Personas'. The 'Selected Entities' column shows '0 selected' for each category.


At the bottom right, there are 'Cancel' and 'Save' buttons.

Review the service and use the slider to activate the service.


The service can be added in deactivated status and activated later when necessary.

Click "Save" on bottom right to save settings and close this screen.


19. Click on “Services Management” to navigate back to Services Management screen.



20. Click on “Credentials” menu as shown below.



21. Click “ADD” to add a new user or click on the pencil icon to edit attributes of an existing user:



(Continued on next page.)

22. Enter the following user credentials on the screen below:


- a. Name of LoanBeam (EPC) user
- b. Description (optional, but recommended)
- c. Credentials – these are the same credentials as required to access the LoanBeam application:

- i. Username
- ii. Password
- iii. API Key (copied from LoanBeam application)

Note – Only one set of LoanBeam Admin credentials are needed for the API. It is NOT required that each individual user's LoanBeam credentials are set up.

- d. Users - Select an individual or group entity to provide access.

Click "Save" to save the new credentials.



The screenshot shows the 'Edit User Credentials' form in the Encompass Admin interface. The form is titled 'Edit User Credentials' and is located under 'Services Management / Credentials /'. The form includes the following fields and sections:


- Name ***: A text input field.
- Description**: A text input field.
- Credentials**: A section containing three fields:
 - Username ***: A text input field.
 - Password ***: A password input field with a masked password.
 - API Key ***: A text input field with a masked API key.
- Users**: A section with a table for selecting users. The table has a 'Category' column and a '0 selected' indicator. The categories are:
 - Organizations
 - Users
 - Personas
- Selected Entities**: A section with a table for selecting entities. The table has a '0 selected' indicator. The selected entity is:
 - EllieMae Test (lo15)

At the bottom right of the form, there are 'Cancel' and 'Save' buttons.

(Continued on next page.)

Important Note: The user will get the below error if there is an error with the account:

- *Unable to process your request. Please contact your Encompass Administrator.*



The user must contact his/her administrator to review their LoanBeam credentials.

- The API Key will not be recognized if a space was entered after the credentials.